



Fiery JobFlow Pro installation guide

Fiery JobFlow Pro provides a browser-based prepress workflow that allows you to define and automate repetitive tasks such as PDF conversion, preflight, correction of PDF files, image enhancement, document imposition.

Fiery JobFlow Pro can be installed on Windows Server 2025, Windows 11 23H2 (version and later) client computers.

Fiery JobFlow Pro system requirements

For system requirements, see <https://assistance.fiery.com/jobflowpro/specs/>.

Fiery JobFlow Pro installation option

Fiery Command WorkStation 7.1 and later, and Fiery Impose are required to use the `fiery-impose` node in Fiery JobFlow Pro Editor.

Install Fiery JobFlow Pro

Before you begin, make sure you are logged in to your Fiery Account.

JobFlow Pro is installed using Fiery Software Manager, which is part of the Fiery Workflow Applications.

- 1 Open Fiery Software Manager.
- 2 Click **Install** next to JobFlow Pro.

After the installation is complete, a JobFlow Pro shortcut is created on your desktop.

Note: During installation of JobFlow Pro, the installer automatically detects the drive which has more free space and creates a folder called `JobFlowProFolders`.

Activate the JobFlow Pro license

Fiery JobFlow Pro requires a license that must be activated from the Fiery JobFlow Pro home page.

- 1 Double-click the JobFlow Pro shortcut on your desktop and create your login information for JobFlow Pro.
- 2 Sign in to JobFlow as Admin and type **Fiery.1** in the **Password** field.

Note: For security reasons, the administrator must change the default administrator password before continuing.

- 3 Click **Add License** in the window that appears on the **Home** tab.



- 4 On the **License activation** page, click **Activate**, and then click **Continue** to agree to the terms and conditions of the license agreement.
- 5 Type your License Activation Code (LAC) in the field and click **Continue**.
- 6 Click **Activate**.
- 7 Click **Finish**.
- 8 Return to the Fiery JobFlow Pro home page and refresh the page to access the licensed version.

If the activation requires a restart, you can either click **Restart** to restart now or click **Finish** if you want to activate additional options before restarting. If the activation does not require a restart, click **Finish**.

Updating Fiery JobFlow Pro

Fiery Software Manager manages updates to Fiery JobFlow Pro. You must update Fiery JobFlow Pro regularly to obtain the latest features, fixes, enhancements, and verification standards. You will have the best user experience when Fiery JobFlow Pro is at the latest version.

Uninstalling Fiery JobFlow Pro from a Windows computer

You can uninstall Fiery JobFlow Pro from a Windows computer through Windows or the Fiery Software Manager.

Uninstall Fiery JobFlow Pro in Windows Settings

- 1 From the Windows desktop, right-click the **Start** button.
- 2 Click **Settings > Apps**.
- 3 Click **Installed apps**.
- 4 Click the **More options** icon next to Fiery JobFlow Pro.
- 5 Select **Uninstall**.
- 6 Follow the on-screen instructions.

Uninstall Fiery JobFlow Pro in Fiery Software Manager

- 1 From the Windows desktop, click Fiery Software Manager.
- 2 Click the **Remove** icon next to Fiery JobFlow Pro.
- 3 Follow the on-screen instructions.

Accessing Fiery JobFlow Pro Help

To access *Fiery JobFlow Pro Help*, sign in to Fiery JobFlow Pro and click **Help** in the lower left corner Fiery JobFlow Pro webpage.

For additional information or support, registered users may start a discussion through [Fiery Communities](#).